USER GUIDE

VERSION 3.1

Enhanced Volume Profile

Session structure for execution decisions.

Designed for NinjaTrader 8 and 1-minute execution charts

Opening Bell | Asian Session | NQ-focused workflow

Built for execution clarity.
Designed for serious traders.

The Algo Trader, LLC | All Rights Reserved



QUICK START

EVP v3.1 in 60 seconds

Choose the calculation source first. That one decision has the greatest effect on loading time, delta behavior, and how closely two charts will match.

1. Choose a profile source

Order Flow Volumetric when available.
Tick Replay when Volumetric is unavailable and trade-level history is needed.
1-Minute Regular Bars for the fastest, broadest compatibility.

2. Use the universal delta default

Start with Up/Down Tick. It works across all three sources. Select Bid/Ask only when you know the chosen source and historical feed support it.

3. Publish on bar close

Bar Close is the recommended setting for historical loading and normal execution. Intrabar Throttled is available when you want a developing live profile between closes.

4. Match the chart session

EVP follows the chart's Trading Hours and EOD boundaries. Use the correct Opening Bell or Asian template before comparing levels with another trader.

Session starting points

SESSION	BEST SOURCE	BEST ALTERNATIVE	FASTEST CHOICE	PUBLISH
Opening Bell	Order Flow Volumetric	Tick Replay	1-Minute Regular Bars	Bar Close
Asian	Order Flow Volumetric	Tick Replay	1-Minute Regular Bars	Bar Close

Two sessions, handled automatically
EVP v3.1 internally processes and retains the current and previous chart-defined profile sessions. MaxSessionsToKeep is not a user setting.

The Algo Trader, LLC | All Rights Reserved

INSTALLATION

Import the Enhanced Volume Profile Version 3.1 ZIP

Use NinjaTrader's standard assembly removal and NinjaScript import workflow. No source-code editing is required.

1. Remove the old version

In the NinjaTrader Control Center, select:

Tools > Remove NinjaScript Assembly

Select the old Enhanced Volume Profile assembly and remove it.

2. Restart NinjaTrader

Close NinjaTrader completely, then reopen it before importing Version 3.1. This gives the platform a clean start after the old assembly is removed.

3. Import Version 3.1
From the Control Center, select Tools > Import > NinjaScript Add-On, choose the Enhanced Volume Profile Version 3.1 ZIP file, and complete the import. In the Indicators window and on the chart, the indicator is shown as EVP v3.1.

How EVP forms a session profile

- The current profile contains only participation from the active chart-defined session, from its start through the latest processed source bar or trade.
- The immediately previous completed profile session is retained separately for prior VAH, VAL, POC, and PVA reclaim references.
- Previous-session volume is never merged into the current developing profile.
- Even when 30 days are loaded, EVP limits its own profile work to the current and previous chart-defined sessions.

Session boundaries come from the chart
The strategy's preferred trading window does not close the profile. The chart's Trading Hours template and EOD definition control when EVP completes one profile and begins the next.

The Algo Trader, LLC | All Rights Reserved

DECISION GUIDE

Choose the right profile source

All three sources live inside the same EVP indicator. Select one source intentionally and keep it the same when comparing charts.

SOURCE	BEST WHEN	REQUIREMENTS	LOAD PROFILE	WHAT TO EXPECT
Order Flow Volumetric	You want detailed volume at each price with native price-level delta handling.	Order Flow Volumetric access and compatible historical data.	Efficient inside EVP	Preferred source for both execution sessions when available.
Tick Replay	Volumetric is unavailable and you want historical Last trades reconstructed price by price.	Historical tick data plus Tick Replay enabled on the chart.	Heaviest chart load	Strong alternative for Asian and Opening Bell analysis.
1-Minute Regular Bars	You prioritize speed, broad compatibility, or run several execution charts.	Standard one-minute historical data.	Fastest	Calculations use regular bars in the background while Heiken Ashi stays visible.

When Volumetric makes sense

Use it when your account supports it and you want the richest price-level history without relying on the visible Heiken Ashi OHLC values. It is especially useful in thin or rapidly changing auction conditions.

When 1-Minute Regular Bars makes sense

Use it for the fastest loading, slow PCs, multi-chart workspaces, or users without Order Flow access. It is the universal starting point and keeps the Heiken Ashi display separate from the calculation source.

Comparison rule
Do not judge a screenshot from Order Flow Volumetric against one built from Tick Replay or 1-Minute Regular Bars. Source mode is part of the chart configuration.

The Algo Trader, LLC | All Rights Reserved

SESSION PLAYBOOK

Opening Bell: recommended setup

The Opening Bell System is normally used from 6:00 a.m. to 10:00 a.m. EST, but the EVP profile remains active until the chart-defined 4:15 p.m. EOD.

PRIORITY	PROFILE SOURCE	USE IT WHEN	RECOMMENDED SETTINGS
1 - Preferred	Order Flow Volumetric	Your account supports it and you want the strongest price-level detail.	Up/Down Tick | Bar Close
2 - Alternative	Tick Replay	Volumetric is unavailable and the computer can comfortably load historical ticks.	Up/Down Tick | Bar Close | Tick Replay ON
3 - Performance	1-Minute Regular Bars	Fast startup and low resource use matter most.	Up/Down Tick | Bar Close

Suggested NQ starting point

Value Area: 70%
Profile Resolution: 8 ticks
Delta: Up/Down Tick
Publish: Bar Close
VA width: Points or Ticks by preference

Trading window vs profile EOD

The preferred execution window ends at 10:00 a.m.; the profile does not. EVP continues accumulating the active chart session until the 4:15 p.m. EOD. The prior profile is the prior complete chart session, not only its 6:00-10:00 window.

Opening Bell operating notes

- Confirm the exact contract month, Trading Hours template, time zone, and EOD setting before comparing levels.
- Expect the chart-defined profile to continue developing after the recommended 10:00 a.m. execution cutoff.
- Expect the developing value area to change quickly during the first part of the session.
- Use Bar Close while loading history. Enable Intrabar Throttled only if you need developing live updates.
- If Tick Replay is slow, switch the profile source to 1-Minute Regular Bars or reduce chart history on a dedicated execution chart.

Best practical answer
Use Order Flow Volumetric when available. Otherwise use Tick Replay on a capable PC. Use 1-Minute Regular Bars when performance and compatibility are the priority.

The Algo Trader, LLC | All Rights Reserved

SESSION PLAYBOOK

Asian Session: recommended setup

The Asian profile runs from 6:00 p.m. through its 11:59 p.m. EOD. The thinner auction makes source consistency especially important.

PRIORITY	PROFILE SOURCE	USE IT WHEN	RECOMMENDED SETTINGS
1 - Preferred	Order Flow Volumetric	Available on the account and detailed price-level volume is desired.	Up/Down Tick | Bar Close
2 - Alternative	Tick Replay	Volumetric is unavailable and historical tick reconstruction is desired.	Up/Down Tick | Bar Close | Tick Replay ON
3 - Performance	1-Minute Regular Bars	The PC is slower, multiple charts are open, or startup speed matters most.	Up/Down Tick | Bar Close

Why source choice matters

A thinner auction can expose differences between one-minute history, reconstructed ticks, and Volumetric rows more clearly than a busy session. Stay with one source when learning its behavior.

Profile boundary

The current Asian profile begins at 6:00 p.m. and completes at the chart-defined 11:59 p.m. EOD. It remains isolated from the previous Asian profile, which is retained only as a separate reference.

Asian Session operating notes

- Apply the correct 6:00 p.m. to 11:59 p.m. Trading Hours template and EOD definition.
- Do not compare an early-session value area with a later screenshot; the first bars carry a larger share of developing structure.
- Keep Up/Down Tick as the default delta method unless you have verified Bid/Ask historical support.
- If a value area looks unexpectedly wide, first verify the contract, source, session template, and data history before changing EVP logic settings.

Best practical answer
Use Order Flow Volumetric when available. Otherwise use Tick Replay. Select 1-Minute Regular Bars when the machine needs the lightest workflow.

The Algo Trader, LLC | All Rights Reserved

PERFORMANCE

Tick Replay: when and how to use it

Tick Replay is powerful because it reconstructs historical Last trades in sequence. That detail also requires more chart resources.

Use Tick Replay when

- Order Flow Volumetric is unavailable.
- You want price-by-price Last-trade history.
- You are reviewing the Asian session.
- You are validating a detailed Opening Bell profile.
- Your PC can handle the requested chart history.

Recommended EVP settings

Profile Source: Tick Replay
Delta Method: Up/Down Tick
Publish Mode: Bar Close
Chart Data Series: Tick Replay enabled
Sessions inside EVP: current + previous

Enable Tick Replay in NinjaTrader
1. From the NinjaTrader Control Center, select Tools > Settings > Market Data, then check Show Tick Replay.
2. Open the chart's Data Series window and check Tick Replay.
3. In EVP, set Profile Source to Tick Replay.

Important for slower PCs
EVP v3.1 skips heavy calculations on older sessions, but Tick Replay is a NinjaTrader chart setting. NinjaTrader must still reconstruct the tick history requested by the chart before EVP can use the final two sessions.

If loading is too slow

- Keep Publish Mode on Bar Close during historical loading.
- Reduce Days to Load on the execution chart. Two to five days is a practical troubleshooting range.
- Consider a separate short-history execution chart while retaining a longer-history context chart without Tick Replay.
- Avoid enabling Tick Replay on several high-volume charts at the same time.
- Use Profile Resolution 8 ticks as a clean NQ starting point before selecting finer rows.
- Select 1-Minute Regular Bars when reliable startup speed is more important than tick reconstruction.

Avoid unnecessary replay
Do not enable Tick Replay on the chart when Profile Source is 1-Minute Regular Bars or Order Flow Volumetric. It adds chart work without benefiting the selected EVP source.

The Algo Trader, LLC | All Rights Reserved

CONSISTENCY

Why EVP can look different on another computer

The same visible symbol and clock time do not guarantee the same underlying history. Most differences are configuration or data differences, not an indicator failure.

CHECK	WHY IT MATTERS	WHAT TO MATCH
Profile source	Volumetric, Tick Replay, and one-minute history are different inputs.	Use the same Profile Source.
Delta method	Up/Down Tick and Bid/Ask classify participation differently.	Use the same Delta Method.
Data provider	Feeds may filter, timestamp, or package historical trades differently.	Use the same feed when exact comparison matters.
Instrument	Contract month, continuous contracts, and rollover/merge settings can differ.	Match the exact contract and merge policy.
Trading Hours	Session begin, end, EOD, holidays, and time zone define the profile boundary.	Match template and platform time zone.
Loaded history	Chart start history can affect what is available and how Heiken Ashi bars develop.	Match Days to Load or Start Date.
EVP settings	Resolution, value percentage, node settings, and publication mode change output.	Load the same saved v3.1 template.

Usually normal

Small differences in delta-bar color, node placement, or developing values can occur when feeds differ. The total chart context should still be evaluated using the same source and session definition.

Investigate immediately

A materially different POC or very wide VA should trigger a check of source mode, exact contract, Trading Hours, EOD, Tick Replay state, and historical data before changing indicator settings.

Screenshot rule
When sharing a screenshot, include the instrument, contract month, session template, Profile Source, Delta Method, Publish Mode, Profile Resolution, and Tick Replay state.

The Algo Trader, LLC | All Rights Reserved

CORE CONTROLS

Settings that shape the profile

Start with the recommended values and change one setting at a time. Consistency matters more than constant tuning.

SETTING	STARTING POINT	WHAT IT CONTROLS	PRACTICAL GUIDANCE
Value Area (%)	70	How much session volume forms accepted value.	Leave at 70 unless your method specifically requires a different value definition.
Profile Resolution (Ticks)	8 for NQ	The price-row granularity of the profile.	Lower values show more rows and use more work. Higher values create a smoother structure.
Profile Source	1-Minute Regular Bars	The historical input used to construct EVP.	Use the session playbooks to select Volumetric or Tick Replay when appropriate.
Delta Method	Up/Down Tick	How volume is classified into positive and negative participation.	Use Bid/Ask only when the selected source and feed support it.
Publish Mode	Bar Close	How often developing calculations are published.	Use Intrabar Throttled only when live between-bar updates are needed.
VA Width Units	Points or Ticks	How VA Spread is presented in the statistics.	Points are intuitive for larger context; ticks are useful for execution precision.

Visual controls

Profile and delta display

Profile Opacity controls transparency. Show Delta Bars is unchecked by default to keep the chart clean; enabling it does not change POC, VAH, VAL, or calculations.

Statistics

Show Statistics controls the fixed information display. Statistics Position moves it to a clear chart corner. Show POC Delta is enabled by default and may be unchecked independently.

Clean v3.1 defaults
Show Delta Bars starts unchecked. Show POC Delta starts checked but can be hidden independently. Acceptance Bars and Acceptance Band (Ticks) both start at 2. EVP automatically handles the current and previous profile sessions.

The Algo Trader, LLC | All Rights Reserved

AUCTION MAP

Levels and deviation bands

The lines describe where the auction has accepted volume and how far price has stretched from the session's most active area.

POC - gold

The Point of Control is the price with the greatest session volume. Treat it as the session's primary agreement reference, not an automatic entry signal.

VAH and VAL - magenta

Value Area High and Value Area Low mark the boundaries of accepted value. Inside suggests balance; sustained trade outside can indicate initiative activity.

POC Deviation Bands - blue

The standard v3.1 multiplier is 1.50. These bands describe normal statistical stretch around the POC-based distribution.

Deviation Extremes - red

The standard v3.1 extreme multiplier is 2.50. These are higher-stress areas where continuation or responsive activity may become more important.

Reading the map

- Inside value: the auction is operating around accepted prices.
- Outside value: price is testing whether a new area can gain acceptance.
- At a deviation band: evaluate participation and structure before assuming reversal or continuation.
- At an extreme: risk and opportunity may both be elevated; require confirmation from your execution framework.

Current and prior references
Current POC is solid gold and current VAH/VAL are solid magenta. Prior-session VAH/VAL are thin dashed magenta. EVP v3.1 no longer plots a separate prior-session POC line. These levels are structural references, not automatic entry signals.

The Algo Trader, LLC | All Rights Reserved

STRUCTURE MANAGEMENT

Nodes and acceptance

EVP identifies concentrated and thin areas, then retires levels after the market demonstrates meaningful acceptance beyond them.

HVNs

High Volume Nodes identify areas where business concentrated. These zones often represent acceptance, rotation, or a reference area on a revisit.

LVNs

Low Volume Nodes identify thinner structure. Price may travel through them quickly or react near their edges, depending on participation.

CONTROL	DEFAULT	WHAT IT DOES
Max HVN / LVN Zones	3 / 3	Limits how many high-volume and low-volume zones appear. Lower counts keep execution charts cleaner.
Min Node Strength (0-1)	0.12	Requires a minimum prominence relative to the session's strongest profile row.
Min Node Spacing (Ticks)	8	Prevents selected node centers from clustering too closely.
Node Smoothing	5	Smooths neighboring profile rows before detection and reduces minor nodes.
HVN / LVN Zone Radius	4 / 2 ticks	Extends each shaded zone this many ticks above and below its detected center price.
Use Statistical Node Filter	On	Adds a statistical volume test after enough profile price levels are available.
Min Levels for Statistics	20	Waits for 20 profile price levels before the statistical filter activates; standard node detection is used before then.

Acceptance controls

- Hide Accepted Levels: retires a level after price demonstrates acceptance beyond it with sufficient participation.
- Acceptance Bars: base number of consecutive qualifying closes required; the v3.1 default is 2.
- Acceptance Band (Ticks): base distance beyond a level that a close must reach; the v3.1 default is 2.
- EVP v3.1 evaluates acceptance on completed-bar publication, keeping historical and real-time behavior aligned.

The Algo Trader, LLC | All Rights Reserved

PARTICIPATION

Control, POC Delta, and VA Spread

The fixed statistics describe accumulated participation and structure. They provide context; they do not forecast the next price move.

Up/Down Tick - recommended

A trade above the prior Last price is classified positive; a trade below is classified negative; unchanged trades follow the prior direction. This method is available across all v3.1 sources.

Bid/Ask - optional

Use only when your selected source and historical feed support dependable Bid/Ask classification. Results can differ from Up/Down Tick even when the total volume profile is similar.

DISPLAY	WHAT IT TELLS YOU	HOW TO USE IT
Control	Profile-wide participation balance: Balanced, Weak Bulls/Bears within balance, or Strong Bulls/Bears with directional pressure.	Use it as the broad session reading; it is not a trade signal.
POC Delta	Net buying or net selling accumulated specifically at the current POC price row.	The percentage is net delta divided by total volume at the POC.
VA Spread	The distance between VAH and VAL in the selected display unit.	Compare width only when source, session, and settings match.
Source line	The active profile source shown in the stats area.	Include it in shared screenshots and troubleshooting.

POC Delta strength bands

0-9%: Balanced
10-24%: Mild
25-39%: Moderate
40-59%: Strong
60%+: Extreme

Example: POC Delta: Moderate Sell Bias | 30% Net Selling

What the percentage means

POC Delta: Balanced | 1% Net Buying means buy-classified volume exceeded sell-classified volume by 1% of all volume accumulated at the POC. The display uses words instead of an unexplained plus or minus sign.

Both delta displays are optional
Show Delta Bars is unchecked by default because many traders prefer a cleaner chart. Show POC Delta is a separate toggle: uncheck it if the POC-specific reading does not improve your decisions. Control, VA Spread, and the profile continue normally.

The Algo Trader, LLC | All Rights Reserved

RECLAIM MONITORING

PVA: prior-session value-area reclaims

PVA monitoring evaluates failed excursions around the completed prior session's stable VAH and VAL. It remains enabled by default in v3.1, with optional real-time sound alerts.

PVA Bull event

Price closes far enough below the prior VAL to begin an excursion, then re-enters the prior value area while the enabled timing and participation filters remain valid.

PVA Bear event

Price closes far enough above the prior VAH to begin an excursion, then re-enters the prior value area while the enabled timing and participation filters remain valid.

Visible structural reference lines

REFERENCE	APPEARANCE	PURPOSE
Prior VAH / VAL	Thin dashed magenta	Stable completed value-area boundaries used by PVA monitoring.
Current VAH / VAL	Solid magenta	Live developing boundaries for the active chart-defined session.
Current POC	Solid gold	Live developing point of greatest profile volume.

- Prior VAH and VAL remain fixed because they come from the completed profile session.
- EVP v3.1 no longer projects a separate prior-session POC line.
- PVA monitoring is separate from DVA monitoring; either feature may be enabled without the other.
- The prior completed session follows the chart's EOD boundary: 4:15 p.m. for the Opening Bell chart and 11:59 p.m. for the Asian chart.

No PVA triangles or text in v3.1
The reclaim-detection backend remains available for an optional sound alert, but v3.1 intentionally does not draw PVA confirmation triangles or PVA Bull/Bear text. The dashed prior VA lines remain the trader's visual reference.

The Algo Trader, LLC | All Rights Reserved

RECLAIM MONITORING

DVA: developing value-area reclaims

DVA monitoring evaluates the active session's developing value area. It remains optional and starts unchecked because the live VAH and VAL can change as the session evolves.

DVA Bull event

An eligible excursion begins below the developing VAL. If price returns through the internally captured reclaim reference while the enabled filters remain valid, the event can trigger an optional real-time sound alert.

DVA Bear event

An eligible excursion begins above the developing VAH. If price returns through the internally captured reclaim reference while the enabled filters remain valid, the event can trigger an optional real-time sound alert.

What remains visible

- The live solid-magenta VAH and VAL continue developing normally throughout the active chart-defined session.
- EVP still captures the relevant value reference internally when an eligible excursion begins.
- The internal reference does not alter or freeze the live value-area calculation.
- EVP v3.1 does not draw the former purple frozen reference band, DVA setup label, confirmation triangle, or DVA Bull/Bear text.

When monitoring begins

Minimum Bars Before DVA Signals lets the developing profile mature first. Min Excursion then determines how far price must close beyond VAH or VAL before an event can begin.

When monitoring ends

The event expires after Max Reversion Bars or is rejected when enabled acceptance and participation requirements are not satisfied. Signal Cooldown Bars controls the spacing between qualifying alerts.

Enable DVA intentionally
Enable Developing VA Reclaim Signals activates the detection logic; Enable Sound Alerts must also be checked if you want an audible notification. Neither setting turns the developing VAH or VAL lines on or off.

The Algo Trader, LLC | All Rights Reserved

RECLAIM CONTROLS

How v3.1 controls detection and alerts

These settings govern internal reclaim qualification, timing, and optional real-time sound alerts. Change one setting at a time and evaluate it over several complete sessions.

SETTING	V3.1 DEFAULT	PLAIN-LANGUAGE PURPOSE
Enable Prior VA Reclaim Signals	On	Activates PVA reclaim detection around the completed prior session's stable value area.
Enable Developing VA Reclaim Signals	Off	Activates optional DVA reclaim detection around the active session's developing value area.
Max Reversion Bars	10	Limits how long a reclaim may take after the excursion begins.
Min Excursion (Ticks)	2	Requires price to close far enough beyond the reference boundary to start a setup.
Min Bars Before DVA Signals	15	Lets the active profile mature before developing-value setups can begin.
Require Participation Slowdown	On / 15%	Requires adverse participation to weaken before confirmation.
Require Failed Acceptance	On	Rejects a reclaim after sustained participation establishes acceptance outside value.
Require Engulfing Confirmation	Off	Optional strict candle-pattern filter; works with the regular one-minute signal bars.
Min Reclaim Delta (%)	5	Requires minimum directional participation on the reclaim bar.
Signal Cooldown Bars	3	Prevents another qualifying alert from the same tracker and direction until enough bars pass.
Enable Sound Alerts	Off	Plays the selected NinjaTrader sound when a valid reclaim confirms in real time.
Sound File	Alert1.wav	Selects the NinjaTrader sound used for a real-time reclaim alert.

Reclaim monitoring is silent by default
EVP v3.1 does not draw reclaim triangles, text labels, or frozen DVA bands. Enable Sound Alerts if you want a real-time notification when the retained PVA or DVA logic confirms an event.

If the baseline is too strict
First consider Max Reversion Bars between 15 and 20 or Participation Slowdown near 10%. Keep Min Reclaim Delta near 5% and avoid disabling several confirmation filters at once. Min Excursion is the setting most likely to need symbol-specific adjustment.

The Algo Trader, LLC | All Rights Reserved

POC ANALYSIS

Use the POC line first

The solid gold POC line already shows where the active session's greatest volume is located. Version 3.1 removes the migration-statistics reading and keeps only the clearer, decision-ready POC tools.

CONTROL	DEFAULT	WHAT IT ADDS
Show POC Delta	On	Displays clearly worded net buying or net selling accumulated at the current POC row.
Show Developing POC Trail	Off	Draws a thin white step trail through completed-source-bar POC locations.

Control is the broad reading

Control summarizes participation across the active profile. Balanced, Weak Bulls/Bears, and Strong Bulls/Bears describe the broader session condition.

POC Delta is the local reading

POC Delta examines only the volume accumulated at the current POC price. It may differ from Control because one price row can have a different imbalance than the full profile.

- POC Delta: Balanced | 1% Net Buying means net buying equals 1% of total volume accumulated at the current POC.
- POC Delta: Moderate Sell Bias | 30% Net Selling means net selling equals 30% of total volume accumulated at the current POC.
- Uncheck Show POC Delta if the POC-specific reading does not add value to your process.
- Enable Show Developing POC Trail only when the historical step path helps you read where the POC has moved; the trail adds no separate migration statistic.

Direction is not prediction
Net Selling while price rises may reflect seller absorption or trapped selling; Net Buying while price falls may reflect buyer absorption or trapped buying. POC Delta describes participation at one price and must be read with price response and structure.

The Algo Trader, LLC | All Rights Reserved

VERSION 3.1

What changed and how to troubleshoot

Version 3.1 removes low-value chart elements and interpretation-heavy statistics while preserving the profile sources, chart-defined sessions, structural levels, and reclaim-detection backend.

Version 3.1 refinements

- POC Delta now uses explicit wording such as 1% Net Buying or 30% Net Selling instead of an unexplained signed percentage.
- Show POC Delta remains an independent toggle so traders can remove the POC-specific reading without hiding Control or VA Spread.
- The POC Migration statistics line and its interpretation settings are removed; the optional Developing POC Trail remains available.
- The prior-session POC line, frozen DVA reference band, DVA setup label, reclaim triangles, and reclaim text labels are removed to reduce chart clutter.
- PVA and DVA detection, participation slowdown, failed acceptance, optional engulfing, excursion, reversion-window, delta, cooldown, and optional sound alerts remain available.
- Current POC, current VAH/VAL, and prior-session VAH/VAL remain the primary structural references.
- Acceptance Bars and Acceptance Band (Ticks) now default to 2.
- The indicator appears in NinjaTrader as EVP v3.1.

SYMPTOM	FIRST CHECK	ACTION
No Tick Replay profile	Tick Replay source selected but chart replay is off.	Enable Show Tick Replay, chart Tick Replay, and then select the Tick Replay source.
Calculation is slow	Too much tick history or too many replay charts.	Use Bar Close, reduce Days to Load, or select 1-Minute Regular Bars.
EVP differs from another PC	Source, feed, contract, session, EOD, or settings differ.	Work through the consistency checklist before changing logic.
No reclaim sound	Sound alerts are off, DVA monitoring is off, or confirmation filters were not satisfied.	Enable Sound Alerts and the desired reclaim monitor; sounds occur only for real-time confirmations.
POC Delta is missing	Show Statistics or Show POC Delta is unchecked.	Enable both settings if you want the POC-specific line in the fixed display.
VA looks unusual	Wrong source, Trading Hours, EOD, or incomplete history.	Verify chart configuration before changing profile settings.

Final guidance
EVP v3.1 is a cleaner structure map, participation gauge, and stretch detector, with optional reclaim sound alerts. It does not replace trade location, confirmation, risk control, or disciplined execution.

For education and chart-analysis purposes. Users are responsible for their data subscriptions, platform configuration, and trading decisions.

The Algo Trader, LLC | All Rights Reserved